

```
ATDES amd64.vmx - sakura 2.0.5.0
ファイル(F) 編集(E) 変換(C) 検索(S) ツール(T) 設定(O) ウィンドウ(W) ヘルプ(H)
0 1 2 3 4 5 6 7 8 9
16 floppy0.autodetect = "TRUE"
17 ethernet0.present = "TRUE"
18 ethernet0.virtualDev = "e1000"
19 ethernet0.wakeOnPcktRcv = "FALSE"
20 ethernet0.addressType = "generated"
21 usb.present = "TRUE"
22 ehci.present = "TRUE"
23 sound.present = "TRUE"
24 sound.fileName = "-1"
25 sound.autodetect = "TRUE"
26 serial0.present = "TRUE"
27 serial0.startConnected = "FALSE"
28 serial0.autodetect = "TRUE"
29 pciBridge0.present = "TRUE"
30 pciBridge4.present = "TRUE"
31 pciBridge4.virtualDev = "pciRootPort"
32 pciBridge4.functions = "8"
33 pciBridge5.present = "TRUE"
34 pciBridge5.virtualDev = "pciRootPort"
35 pciBridge5.functions = "8"
36 pciBridge6.present = "TRUE"
37 pciBridge6.virtualDev = "pciRootPort"
38 pciBridge6.functions = "8"
39 pciBridge7.present = "TRUE"
40 pciBridge7.virtualDev = "pciRootPort"
41 pciBridge7.functions = "8"
42 vmci0.present = "TRUE"
43 roamingVM.exitBehavior = "go"
44 displayName = "ATDES amd64"
45 guestOS = "debian5-64"
46 nvram = "ATDES amd64.nvram"
47 virtualHW.productCompatibility = "hosted"
48 printers.enabled = "FALSE"
49 extendedConfigFile = "ATDES amd64.vmx"
50 ethernet0.generatedAddress = "00:0c:29:d8:93:19"
51 uuid.location = "56 4d d1 67 0e 3c 60 1e-e9 11 36 57 9b d8 93 19"
52 uuid.bios = "56 4d d1 67 0e 3c 60 1e-e9 11 36 57 9b d8 93 19"
53 cleanShutdown = "TRUE"
54 replay.supported = "FALSE"
55 replay.filename = ""
56 scsi0:0.redo = ""
57 pciBridge0.pciSlotNumber = "17"
58 pciBridge4.pciSlotNumber = "21"
59 pciBridge5.pciSlotNumber = "22"
60 pciBridge6.pciSlotNumber = "23"
61 pciBridge7.pciSlotNumber = "24"
62 scsi0.pciSlotNumber = "18"
63 usb.pciSlotNumber = "32"
64 ethernet0.pciSlotNumber = "33"
65 sound.pciSlotNumber = "34"
66 ehci.pciSlotNumber = "35"
67 vmci0.pciSlotNumber = "36"
68 vmotion.checkpointFBSize = "33554432"
69 ethernet0.generatedAddressOffset = "0"
70 vmci0.id = "-518980530"
71 tools.remindInstall = "FALSE"
72 ide1:0.autodetect = "TRUE"
73 ide1:0.startConnected = "FALSE"
74 checkpoint.vmState = ""
75 tools.syncTime = "FALSE"
76 numvcpus = "1"
77 cpuid.coresPerSocket = "1"
78 hks.enable3d = "FALSE"
79 usb.autoConnect.device0 = "path:1/1/0/1 autoclean:1"
80 usb:1.present = "TRUE"
81 usb:1.deviceType = "hub"
82 usb.autoConnect.device1 = ""
83 serial1.fileName = "COM4"
84 usb:1.speed = "9"
85 softPowerOff = "TRUE"
86 migrate.hostlog = ".#ATDES amd64-ae6b9d39.hlog"
87 monitor.phys_bits_used = "40"
88 isolation.tools.hgfs.disable = "FALSE"
89 sharedFolder0.present = "TRUE"
90 sharedFolder0.enabled = "TRUE"
91 sharedFolder0.readAccess = "TRUE"
92 sharedFolder0.writeAccess = "TRUE"
93 sharedFolder0.hostPath = "C:\armadillo\share"
94 sharedFolder0.guestName = "share"
95 sharedFolder0.expiration = "never"
96 sharedFolder.maxNum = "1"
```

<ポイント1>
⇒ serial0.fileName = "COM3" がないので、
追記をしVMWareを起動し確認したが、
シリアルポートCOM3の認識がない。

<ポイント2>
⇒ そもそもVMWareを起動する前は、
シリアルポートCOM3は認識しているが、
VMWareを起動すると、認識しなくなる。

<ポイント3>
⇒ serial1.fileName = "COM4"
になっている。
何か違うシリアルポートに認識されてしまうのか？